

RELEASE NOTES

Product

ProRAE Studio II

Version

V1.11.6

Operating Systems

Windows 7(x86 and x64), Windows 10

Release Date

April 2019

All users are recommended to update their existing ProRAE Studio II (PRS II) software to v1.11.6.

What's New

This release contains the following enhancements:

1. Butadiene gas has been added to AutoRAE 2 calibration library.

Installation and Update Notes

1. [Download the software](#) from the RAE Systems by Honeywell website.
2. Ensure system requirements (Windows 7 and Windows 10) are met.
3. Double-click **ProRAE_Studio_II_V1.11.6_Web.exe**.
4. Follow the instructions for installation.
5. Once the software is successfully installed, a “**Success**” window appears. Click “**Finish**” to exit the installation program.

Before installation

Close all other programs before installation.

For more information
www.honeywellanalytics.com
www.raesystems.com

Europe, Middle East, Africa
Life Safety Distribution GmbH
Tel: 00800 333 222 44 (Freephone number)
Tel: +41 44 943 4380 (Alternative number)
Fax: 00800 333 222 55
Middle East Tel: +971 4 450 5800 (Fixed Gas Detection)
Middle East Tel: +971 4 450 5852 (Portable Gas Detection)
gasdetection@honeywell.com

Americas
Honeywell Analytics Distribution Inc.
Tel: +1 847 955 8200
Toll free: +1 800 538 0363
Fax: +1 847 955 8210
detectgas@honeywell.com

RAE Systems by Honeywell
Phone: 408.952.8200
Toll Free: 1.888.723.4800
Fax: 408.952.8480

Asia Pacific
Honeywell Analytics Asia Pacific
Tel: +82 (0) 2 6909 0300
Fax: +82 (0) 2 2025 0328
India Tel: +91 124 4752700
analytics.ap@honeywell.com

Technical Services
EMEA: HAexpert@honeywell.com
US: ha.us.service@honeywell.com
AP: ha.ap.service@honeywell.com

RELEASE NOTES

Supported Instruments

• AutoRAE 2 Controller	V1.36
• AutoRAE 2 Cradle for Handheld PID Monitor	V1.36
• AutoRAE 2 Cradle for MicroRAE	V1.36
• AutoRAE 2 Cradle for MultiRAE	V1.36
• AutoRAE 2 Cradle for QRAE 3	V1.36
• AutoRAE 2 Cradle for ToxiRAE Pro	V1.36
• AreaRAE Plus & AreaRAE Pro	V1.08
• GammaRAE II R	V4.01
• MicroRAE	V1.12
• MiniRAE 3000 + & MiniRAE Lite	V2.20
• MultiRAE, MultiRAE Benzene, MultiRAE Lite, MultiRAE Pro	V1.50
• MultiRAE MX	V1.14X
• NeutronRAE II 3020	V2.01
• NeutronRAE II 3021	V3.02
• ppbRAE 3000 +	V2.20
• QRAE II	V3.62
• QRAE 3	V2.16
• ToxiRAE Pro, ToxiRAE Pro CO2, ToxiRAE Pro LEL & ToxiRAE Pro PID	V1.80A
• UltraRAE 3000 +	V2.20

RELEASE NOTES

Previous Versions

ProRAE Studio II v 1.11.5

What's New

This release contains the following enhancements:

1. Support added for MiniRAE 3000 +, ppbRAE 3000 + and UltraRAE 3000 +

ProRAE Studio II v 1.11.4

What's New

This release contains the following enhancements:

1. PH3 Sensor Support

ProRAE Studio II v 1.11.3

What's New

This release contains the following enhancements:

1. Support for latest instrument firmware.

ProRAE Studio II v 1.11.2

What's New

This release contains the following enhancements:

1. Ability to extend the Man Down alarm warning up to 180 seconds
2. Ability to configure the O₂ sensor calibration parameters
3. Additional support for AreaRAE Pro/Plus
 - a. Updated gas library definitions
 - b. Support RCS command on AreaRAE devices
 - c. Correction Factors (CF) for PID & LEL gas libraries can't be set to "0"
4. Ability to modify units of measure (UoM) for EC sensors from ppm to mg/m³ in MicroRAE

ProRAE Studio II v 1.11.1

What's New

This release contains the following enhancements:

1. Menu Update: Moved database synchronization option under Operations
2. Ability to synchronize instrument clock with the local time using templates.

RELEASE NOTES

ProRAE Studio II v 1.11.0

What's New

This release contains the following enhancements:

1. Supports AreaRAE Pro & AreaRAE Plus.
2. Improved user interface for AreaRAE Pro and AreaRAE Plus device configuration.
3. ProRAE Studio II is supported on Windows 10.

ProRAE Studio II v 1.10.1

What's New

This release contains the following enhancements:

1. **Backward compatibility of configuration files for the following products:**
 - ToxiRAE Pro Series
 - MultiRAE Series
 - QRAE 3
 - AutoRAE2

ProRAE Studio II v 1.10.0

What's New

This release contains the following enhancements:

1. Supports MicroRAE and AutoRAE 2 Handheld PID Cradle for ppbRAE 3000, MiniRAE 3000, UltraRAE 3000, MiniRAE Lite and MiniRAE Lite ATEX.
2. Allows transferring device data from ProRAE Studio II to Remote ProRAE Guardian.

ProRAE Studio II v 1.9.1

What's New

This release contains the following enhancements:

1. Supports KM LEL sensor for QRAE 3.
2. Allows setting of QRAE 3 sensor serial number to track sensor production date.
3. Allows software to connect to the Internet using proxy server.

ProRAE Studio II v 1.9.0

What's New

This release contains the following enhancements:

1. Supports MultiRAE MX.
2. New ProRAE Update for checking firmware updates.
3. Custom region setting for wireless modules.
4. Supports strong password policy.
5. Allows secure password reset.